



BEYOND

BARCODES

User Guide



BEYONDIT GmbH

Schauenburgerstr. 116
24118 Kiel
Germany
+ 49 431 3630 3700
hello@beyondit.gmbh

Table of Contents

About this Documentation

- Preface

- General Information

- About this App

Setup

- Your Token

- Install BEYOND Barcodes

- Assign User Permission Set for the Setup

- Set up BEYOND Barcodes

Features

- Define Fields for Barcode Generation

 - Barcodes for Item Nos.

 - QR Codes for Contacts

- Update Barcode Values

- Scan Barcodes

- Create Barcode Print Layout

Frequently Asked Questions

- Troubleshooting and FAQ

Preface

This documentation contains information on how to install and operate **Beyond Barcodes** in your Business Central environment.

This documentation is intended for experienced users of Business Central. Additional knowledge of third-party software products may be required to set up Beyond AdvancedSerialNo.

Read this documentation in full to set up **Beyond Barcodes** and work with it professionally. Pay particular attention to the tips, information and safety instructions contained in the documentation. Inform your employees about the proper use of **Beyond Barcodes** and keep the documentation in a place that is accessible to your employees.

DOWNLOAD
PDF

Manufacturer

Beyond Barcodes is developed by:

BeyondIT GmbH
Schauenburgerstraße 116
24118 Kiel
Germany
info@beyondit.gmbh
[+49 431 3630 3700](tel:+4943136303700)

VISIT
APPSOURCE

Version history

Version	Date	Author	Comment
1.0	03.07.2022	Jannic Weidel	Digitalization of the documentation
1.1	03.28.2022	Jannic Weidel	Added Subtitles for Screenshots
1.2	12.06.2025	Jannic Weidel	Added Preface chapter
Document Access		public	

General Information

This documentation contains important information that you must observe when following the descriptions. The information is highlighted as notes and arranged according to type and importance. The notes are listed below in ascending order of importance:

TIP

This represents **no risk**. In addition to the classic clicking on options, Business Central also offers the option of using so-called shortcuts. Shortcuts are key combinations with which you can also execute the desired action in the user interface. By using shortcuts, you can work faster and more effectively. Try the key combination and you will be surprised how much faster you can work.

NOTE

This represents **no risk**. This note contains important information on the correct use, configuration or operation of the software. Follow these instructions to avoid inefficiencies and unnecessary support tickets. For example, this note can show you that an option is hidden and tells you how to proceed if you want to show it again.

IMPORTANT

This represents a **low risk**. This notice refers to non-critical issues that may lead to undesired behavior or configuration problems. May affect user experience or functionality if not considered.

CAUTION

This represents a **medium risk**. This notice indicates a potential problem that could affect system stability or data integrity. Failure to comply may result in errors, loss of performance or partial service interruptions. The errors caused by non-compliance only affect the app itself and prevent you from working with data within the app.

WARNING

This represents a **high risk**. This notice indicates an immediate and serious risk to the productive system. Failure to observe this warning may affect the entire system. There is a risk of loss of critical data or total system failure, leading to prolonged downtime. It may not be possible to restore the data and a backup must be imported.

Beyond Barcodes is an extension for Microsoft Dynamics 365 Business Central.

Beyond Barcodes extends your Business Central and enables the use of barcodes.

The solution adds a barcode factbox on the item card and item list in Business Central. An API in the background generates barcodes for item numbers or other information you have defined in the barcode setup. The barcodes can also be used as electronic business cards for contacts or employees. The app can be easily and quickly customized to your needs, just contact us.

NOTE

Supported Barcode Formats

The extension supports a variety of barcode formats including Code128, Code128A, Code128B, Code128C, Code39, EAN13, EAN8, EAN5, EAN2, UPC, UPCE, ITF, ITF14, MSI and QR codes.

Use Cases

- **Barcodes for Item Nos**
In this use case, the app is set up to generate barcodes for item numbers. The barcodes can be read using the integrated barcode scanner. The view in Business Central then switches to the item card.
- **QR Codes (electronic business cards) for contacts**
In this use case, we set up the app to generate QR codes with the contact details of the contact stored in Business Central. You can use these QR codes, for example, to send customer contact information to your sales representatives or field staff.

The examples (use cases) described in this documentation represent only a part of the possibilities offered by the **Beyond Barcodes** extension. If you have a specific case that you would like to map using the extension, please contact us.

To get additional information of how you can use this extension, please visit:

- [Beyond Barcodes Example](#)
- [Beyond Barcodes Example Item](#)
- [Beyond Barcodes PowerApp](#)

The latest version of this documentation can be found at the following link: [Beyond Barcodes Documentation](#).

NOTE

No dependencies on or to other apps

No additional, basic applications are required to use **Beyond Barcodes**.

Your Token

Before you can use BEYOND Barcodes, you should contact us, so we can advise you which cost plan is the best for you. The plans available are based on time and/or number of barcodes generated. For more information, please visit <https://www.beyondbarcodes.de/>. We can also support you installing the extension, if needed.

Once you have decided on a cost plan, you will receive two tokens from us:

- **Capacity Token**

The capacity token controls access to your personal barcode API. The capacity token can be limited, i.e. it can only be used to generate a certain number of API calls (create barcodes) each month. When the capacity token is exhausted, you can buy new API calls or wait for the next month. You could also switch the cost plan and access a larger contingent of barcodes, if needed.

- **Manage Token**


The Manage Token controls the administrator area for managing capacity tokens. It is used to create capacity tokens and allocate the associated quotas for API calls.

We recommend that you save the two tokens in a file. The tokens are required for extension setup.

[Next chapter](#)

Install BEYOND Barcodes


BEYOND Barcodes can be downloaded from the Microsoft AppSource or installed directly from Business Central. The following section describes how to install the extension via Business Central.

1. Open your Business Central.
2. From the role center, open the search (**ALT+Q**) .
3. Search for **Extension Marketplace** and click on the corresponding search result. The page **Extension Marketplace** is displayed.
4. Enter **BEYONDIT GmbH** in the search and press ENTER. Searching for BEYONDIT GmbH will ensure that you install the correct extension.
5. Choose **BEYOND Barcodes** from the search results.

The following window is displayed:

×

One more thing ...



BeyondBarcodes
By BEYONDIT GmbH

This app requires some basic profile information. We have pulled your Microsoft Account data to help you get started. AppSource will save your information for next time.

Name *

Work email *

Job title

Company

Country / region *

▼

Phone number *

☐

I give Microsoft permission to use or share my [account information](#) so that the provider or Microsoft can contact me regarding this product and related products and Microsoft may share contact, usage, and transactional information for support, billing, and other transactional activities. I agree to the provider's [terms of use](#) and [privacy policy](#) and understand that the rights to use this product do not come from Microsoft, unless Microsoft is the provider. Use of AppSource is governed by separate [terms](#) and [privacy](#).

Continue

6. Complete the information in the window. Select the checkbox, to allow Microsoft to share these information with us. Click **Continue**. The following window is displayed:

Extension Installation



Review Extension Information before installation

Name	BeyondBarcodes
Publisher	BEYONDIT GmbH
Language	English (United States) ...

[Terms and Conditions](#)

[Privacy Statement](#)

I accept the terms and conditions ☐

[Read more about the best practices for installing and publishing extensions](#)

Back

Install

7. Choose the language for BEYOND Barcodes and click **Install**.

BEYOND Barcodes is installed to your Business Central.

[Next chapter](#)

Assign User Permission Set for the Setup of BEYOND Barcodes

All setup for BEYOND barcodes is done on a dedicated page (**Barcode setup**). Access to this page is restricted to prevent accidental changes to the settings. To set up access to this page for users, users must be assigned the **BYD BBADMIN** permission set.

To assign the **BYD BBADMIN** authorization set to a user, proceed as follows:

- 1. Open your Business Central.
 - 2. From the Role Center, open the search (**ALT+Q**) □.
 - 3. Search for **Permission Sets** and click on the corresponding search result.
- The **Permission Sets** page is displayed.

← Permission Sets

Search	New	Edit List	Delete	Permissions	Copy Permission Set...	Import Permission Sets	Export Permission Sets	Related	Fewer options
Permission Set ↑				Name ▼		Type ↑		Extension Name	
→ BYD BBADMIN				Barcodes Admin		System		BeyondBarcodes	
BYD BBREADER				Barcodes Reader		System		BeyondBarcodes	
BYD BBUSER				Barcodes User		System		BeyondBarcodes	

- 4. You can assign the **BYD BBAdmin** permission set for a single user oder for a user group. For the following description, we assume that you want to set the permission set at the user level. Click **Related > Permissions > Permission Set by User**.

← Permission Sets

Permissions User Groups

Permission Set by User	Cloud Connector Benutzer	User-Defined	
Permission Set by User Group	Cloud Connector Lesezugriff	User-Defined	
Show Permission Conflicts Overview	Barcodes Admin	System	BeyondBarcodes
Show Permission Conflicts	Barcodes Reader	System	BeyondBarcodes
	Barcodes User	System	BeyondBarcodes

- 5. The **Permission Set by User** pag is displayed. From the **Company Name** drop-down menu, select the company for which you want to grant a user access to the BEYOND Barcodes setup page.
- 6. Select the **BYD BBADMIN** permission set from the table and select the check box for this user.

This user now has permission to view the **Barcode Setup** page.

Next chapter

Set up BEYOND Barcodes

This section describes how to set up the BEYOND Barcodes extension for your Business Central. The **Capacity Token** and the **Manage Token** are required for the setup. These are provided by your vendor.

NOTE

User Permission Set Required


To be able to search for the **Barcode Setup** page you need to have the proper user permissions set. Ask your Business Central administrator for the corresponding user permission set. More information about the user permission sets can be found under “**Assign User Permission Set for the Setup**”.

To set up the extension, proceed as follows:


- 1. Open your Business Central.
- 2. From the role center, open the search (**ALT+Q**)
- 3. Search for **Barcode Setup** and click on the corresponding search result.



- 4. The **Barcode Setup** page is displayed.



- 5. Enter the tokens in the fields on the page.
- 6. In the menu bar, click on **Update Capacity**. The fields **Total Capacity**, **Used** and **Remaining** are updated.



The update of the fields indicate that the set up of the extension was completed. The API can now be used to generate barcodes.

Next chapter

Define Fields for Barcode Generation

This section describes how you can define which values (or information) of fields should be displayed as barcodes. We have provided use cases for you to get a better understanding of how you can use the extension.

Barcodes for Item Nos.

Barcodes are often used to represent item numbers. The following use case describes how to set up the extension to generate item numbers as barcodes in Business Central.

To define that item numbers are generated as barcodes, do the following:

1. Open your Business Central.
2. Search for **Barcode Setup** and click on the corresponding search result.
The **Barcode Setup** page is displayed.
3. Scroll down to the **Specifications** table and click on **Manage > New Line**.
4. A new line is added to the table. Add the following information:

Column	Description
Table Name	In this field you specify the table from which you want a field information (to be generated as a barcode) to come from. In our example, you would specify the Item table (ID: 27).
Field Name	In this field you specify the field of the table in which a value is to be created as a barcode. In our example, you would specify the No. field (ID: 1).
Format	In this field you define the format of the barcodes to be generated. You can choose between 15 different formats (including QR codes). In our example we use the Code128 format.
As Electronic Business Card	Select this checkbox if you want an electronic business card to be created. This option should be enabled only if you want to exchange contact information. For our example, this option should not be enabled.
Error Correction	In this field you can define the error correction for the barcode generation. The default setting is medium .
Height	In this field you define the height of the barcodes in pixels. If you do not define a height, the default setting is used. The default setting is 100 pixel.
Margin	In this field you define the margin of the barcodes in pixels. If you do not define a margin, the default value is used. The default value is 10 pixels.
Foreground	In this field you define the color of the barcodes. If you do not define a color, the default setting is used. The default setting is black (#000000).
Background	In this field you define the background color of the barcodes. If you do not define a background color, the default setting is used. The default setting is white (#ffffff).
Barcode Values	This field is automatically filled by the system. This field displays the number of generated barcodes in the system for the table and field combination.

Barcode Setup

Update Capacity

General

Token

Capacity Token

Manage Token

Capacity

Total Capacity

Used

Left

Specifications

Manage

Table Name	Field Name	Format	As Electronic Business Card	Error Correction	Height	Margin	Foreground	Background	Barcode Values
Item	No.	CODE128	<input type="checkbox"/>	medium					23

QR Codes for Contacts

You can also use the extension to create electronic business cards for contacts. These business cards (QR codes) can be used to exchange contact information quickly and easily.

To set up BEYOND Barcodes so that QR codes can be used as electronic business cards, proceed as follows:

- Open your Business Central.
- Search for **Barcode Setup** and click on the corresponding search result.
The **Barcode Setup** page is displayed.
- Scroll down to the **Specifications** table and click on **Manage > New Line**.
- A new line is added to the table. Add the following information:

Column	Description
Table Name	In this field you specify the table from which you want a field information (to be generated as a QR Code) to come from. In our example, you would specify the Contact table (ID: 5050).
Field Name	In this field you specify the field of the table in which a value is to be created as a QR Code. In our example, you would specify the No. field (ID: 1).
Format	In this field you define the format of the barcodes to be generated. You can choose between 15 different formats (including QR codes). In our example we use the QR Code format.
As Electronic Business Card	Select this checkbox if you want an electronic business card to be created. This option should be enabled only if you want to exchange contact information. <u>For our example this option should be selected.</u>
Error Correction	In this field you can define the error correction for the QR code generation. The default setting is medium .
Height	In this field you define the height of the QR Codes in pixels. If you do not define a height, the default setting is used. The default setting is 100 pixel.
Margin	In this field you define the margin of the QR Codes in pixels. If you do not define a margin, the default value is used. The default value is 10 pixels.
Foreground	In this field you define the color of the QR Codes. If you do not define a color, the default setting is used. The default setting is black (#000000).
Background	In this field you define the background color of the QR Codes. If you do not define a background color, the default setting is used. The default setting is white (#ffffff).
Barcode Values	This field is automatically filled by the system. This field displays the number of generated barcodes in the system for the table an field combination.

Barcode Setup

Update Capacity

General

Token

Capacity

Capacity Token

Manage Token

Total Capacity

Used

Left

20000

23

19977

Specifications

Manage

Table Name	Field Name	Format	As Electronic Business Card	Error Correction	Height	Margin	Foreground	Background	Barcode Values
→ Contact	No.	QR Code	<input checked="" type="checkbox"/>	medium	10.00	10.00	-	-	27
Employee	No.	QR Code	<input checked="" type="checkbox"/>	medium	10.00	10.00	-	-	7

The electronic business cards have been set up. To create the business cards, the barcode values must be updated. Once the barcode values are updated (see section [Update barcode values](#)), the business cards (QR codes) will be displayed in the info box area on the right side of the screen.

Contacts

Search

New

Manage

Process

Contact

Navigate


More options

No.	Name T	Company Name T	Contact Business Relation	Phone No.	Email	Salesperson Code	Territory Code
KT000001	Adatum Corporation	Adatum Corporation	Customer		adatum.corporation@contoso.com	DH	
KT000002	Jakob Otto	Adatum Corporation	Customer	+49 431 3630 3700	jakob.otto@contoso.com	DH	
KT000007	Alpine Ski House	Alpine Ski House	Customer		alpine.ski.house@contoso.com	DH	AUSLAND
KT000008	Ian Deberry	Alpine Ski House	Customer		ian.deberry@contoso.com	DH	AUSLAND
KT000024	BEYONDIT GmbH	BEYONDIT GmbH	None	+49 431 3630 3700	hello@beyondit.gmbh	DG	
KT000029	Sascha Fischer	BEYONDIT GmbH	None	+49 431 3630 3777	hello@beyondit.gmbh	DG	
KT000011	Fabrikam, Inc.	Fabrikam, Inc.	Vendor		fabrikam.inc@contoso.com	BK	AUSLAND
KT000012	Krystal York	Fabrikam, Inc.	Vendor		krystal.york@contoso.com	BK	AUSLAND
KT000013	First Up Consultants	First Up Consultants	Vendor		firstup consultants@contoso.com	BK	
KT000014	Falk Neuman	First Up Consultants	Vendor		falk.neuman@contoso.com	BK	

Details

Attachments (0)

Barcode




You can also set up these electronic business cards for your employees.

[Next chapter](#)



Update Barcode Values

If you define a new barcode for your Business Central or if you make changes to an already defined barcode on the setup page, you need to update existing barcodes or create new one for the defined format. This task can be time-consuming if you do it manually. We have added a button which allows you to update the barcode values globally.

To generate barcodes or replace already existing barcodes with batch processing, proceed as follows:


- 1. Open your Business Central.
- 2. From the role center, open the search (**ALT+Q**) .
- 3. Search for **Barcode Setup** and click on the corresponding search result. The page **Barcode Setup** is displayed.
- 4. In the table **Specifications**, click **Manage > Update Barcode Values**.

Specifications | [Manage](#)

 New Line  Delete Line  Update Barcode Values

→	Customer	:	No.	QR Code	<input type="checkbox"/>	medium
	Item		No.	CODE128	<input type="checkbox"/>	medium
	Contact		No.	QR Code	<input checked="" type="checkbox"/>	medium
	Employee		No.	QR Code	<input checked="" type="checkbox"/>	medium

- 5. A dialog is displayed asking you if you want to update the barcode values.

 Do you want to Update Barcode Values?

Yes

No

- 6. Click **Yes**.
- 7. Another dialog is displayed. You are asked if you want to update only existing barcodes.
- 8. If you want to update the existing barcodes, click **Yes**.

The barcodes are generated by the API and will be replaced by the extension.


[Next chapter](#)

Scan Barcodes

The extension adds a barcode scanner to your role center. This barcode scanner can be used with any compatible device with a camera.

For the following description we used a mobile device (Android operating system).


1. Open your Business Central on your mobile device.
2. From the role center, scroll down to the **Barcode Scanner** pane.



3. Tap on the **Scan** tile.


The **Edit – Barcode Scanner** is displayed. To be able to scan barcodes with the camera of your mobile device you need to grant permissions to access the camera.

4. Tap **Request Camera Permissions**.




5. If your mobile device has more than one camera, you need to specify which camera should be used to scan the barcode.

Tap the dropdown symbol next to the option **Select Camera**.



6. Tap **Start Scanning**.

7. Scan the barcode on the item.



The view in your Business Central app is switched to the item card of the scanned item.

Item

Show more

No.

1001

...

Description

BEYONDIT Coffee Mug

Blocked

☐

Type

Inventory

▼

Base Unit of Measure

STÜCK

...

Item Category Code

...

Inventory

Show more

Shelf No.




⋮

[Next chapter](#)


Create Barcode Print Layout

This chapter describes how to create a print layout for barcodes.
To create a print layout for barcodes, proceed as follows:

- 1. Open the search field (ALT+Q) and search for the page **Barcode Print Layouts**.
- 2. The **Barcode Print Layouts** page is displayed.



- 3. To create a new print layout for barcodes, click on the **New** option in the menu bar.
- 4. A new card for a barcode print layout is displayed.



- 5. Enter a code for the print layout in the **Code** field.
- 6. Enter a description for the print layout in the **Description** field.
- 7. Enter a table ID in the **Table ID** field.
- 8. In the **Layout** area, you can set the unit for the size of the barcode print layout.
- 9. Define the width and height of the barcode print layout.
- 10. You can add information to the barcode print layout in the **Lines** area. For example, if you want to create a barcode print layout for items, you can add the following information:

Type	Field ID	Description	Width	Height	X Position	Y Position	Font Size	Txt Alignment	Barcode Source Table ID	No. of Source Table Links
Field	3	Description	-	-	2.00	3.00	6.00	Left	-	-
Barcode	-	-	-	-	2.00	3.00	6.00	Left	-	-

40X20-WO-SP

Copy

Automate

Fewer options

Layout

Units mm

Width 40.00

Height 20.00



Lines										
<div><div>New Line</div><div>Delete Line</div></div>										
	Type		Field Id	Description	Width	Height	X Position	Y Position	Font Size	Text Alignment
→	Field	:	3	Description			9.00	4.00	6.00	Left
	Barcode				30.00	15.00	5.00	5.00		Left

Troubleshooting and FAQ

Question/Problem	Solution
Could you extend the extension so we can use barcodes on other pages than the specified ones?	Please contact us if you want to use the extension in a different way than the specified use cases. We can customize the app to your needs.
Do I need to change the token every month?	The token and the number of barcodes that can be generated with it stays the same. The token is not changed.
I did not receive a token...	Please check the inbox of your email account. Please also check if the mail with the token is in your SPAM.
I want to switch zu a different costing plan.	You can switch to a different costing plan at the beginning of every month (if no other agreements have been made), just contact us.

Contact Details

BEYONDIT GmbH

Schauenburgerstraße 116

24118 Kiel

Germany

info@beyondit.gmbh

[+49 431 3630 3700](tel:+4943136303700)